

[May-2019-New] 300-075 Dumps PDF 467Q Instant Download in Braindump2go

[2019/May Braindump2go Cisco CCNP Collaboration CIPTV2 300-075 Dumps with PDF and VCE New Updated Today!](#)

Following are some new 300-075 Exam Questions:1.|2019 Latest 300-075 Exam Dumps (PDF & VCE) Instant Download:<https://www.braindump2go.com/300-075.html>2.|2019 Latest 300-075 Exam Questions & Answers Instant Download:<https://drive.google.com/drive/folders/0B75b5xYLjSSNOXRpM1hydUpDU3M?usp=sharing>New QuestionIf you want to delete a SAF-enabled trunk from Cisco Unified Communications Manager Administration, what must you do first?A. Disassociate the trunk from the CCD advertising service or CCD requesting service.B. Delete the trunk from the CCD requesting service node.C. Place the Cisco Unified Communications Manager node in standby mode.D. Redirect CCD advertising and requesting services to another Cisco Unified Communications Manager.**Answer:** A New QuestionWhich functionality does ILS use to link all hub clusters in an ILS network?A. FullmeshB. AutomeshC. ILS updatesD. multicast**Answer:** B New QuestionWhich option is known as the location attribute that the global dialplan replication uses to advertise its dial plan information?A. location controllerB. route patternC. route stringD. URI**Answer:** C New QuestionRefer to the exhibit. If an IP phone in San Jose roams to New York, which two IP phone settings will be modified by Device Mobility so that the phone can place and receive calls in New York? (Choose two.) A. The physical locations are not different, so the configuration of the phone is not modified.B. The physical locations are different, so the roaming-sensitive parameters of the roaming device pool are applied.C. The device mobility groups are the same, so the Device Mobility-related settings are applied in addition to the roaming-sensitive parameters.D. The Device Mobility information is associated with one or more device pools other than the home device pool of the phone, so one of the associated device pools is chosen based on a round-robin load-sharing algorithm.E. The Device Mobility information is associated with the home device pool of the phone, so the phone is considered to be in its home location. Device Mobility will reconfigure the roaming-sensitive settings of the phone.**Answer:** BC New QuestionWhat happens when a user logs in using the Cisco Extension Mobility Service on a device for which the user has no user device profile?A. The Extension Mobility log in fails.B. The device takes on the default device profile for its type.C. The user can log in but does not have access to any features, soft key templates, or button templates.D. The device uses the first device profile assigned to the user in Cisco Unified Communications Manager.**Answer:** B New QuestionWhich three steps are required when configuring extension mobility in Cisco Unified Communications Manager? (Choose three.)A. Create the extension mobility IP Phone Service.B. Check the Home Cluster checkbox on the End User Configuration page.C. Check the Enable Extension Mobility checkbox on the Directory Number Configuration page.D. Unsubscribe all other services from the Cisco IP Phone.E. Create a user Device Profile.F. Subscribe the extension mobility IP Phone Service to the user Device Profile.**Answer:** AEF New QuestionHow many Cisco Unified Mobility destinations can be configured per user?A. 1B. 10C. 4D. 6**Answer:** B New QuestionWhen configuring Cisco Unified Mobility, which parameter defines the access control for a call that reaches out to a remote destination?A. Calling Party Transformation Calling Search Space under Remote Destination Profile InformationB. User Local under Remote Destination Profile InformationC. Rerouting Calling Search Space under Remote Destination Profile InformationD. Rerouting Calling Search Space under Remote Destination informationE. Calling Search Space under Phone Configuration**Answer:** C New QuestionWhich two bandwidth management parameters are available during the configuration of Cisco Unified Communications Manager regions? (Choose two.)A. Default Audio Call RateB. Max Audio Bit RateC. Default Video Call RateD. Max Video Call Bit Rate (Includes Audio)E. Max Number of Video Sessions**Answer:** BD New QuestionIn Cisco Unified Communications Manager, where do you configure the default bit rate for audio and video devices?A. Enterprise ParametersB. Region under Region InformationC. Cisco CallManager service under Service Parameter ConfigurationD. Enterprise Phone Configuration**Answer:** C Explanation:For enhanced scalability and to conserve resources, Cisco recommends that you properly set the default values in the Clusterwide Parameters (System - Location and Region) section of the Cisco Unified Communications Manager Administration Service Parameters Configuration window for the audio codec, video call bandwidth, and link loss type values and then choose the Use System Default entries in the Cisco Unified Communications Manager Administration Region Configuration window for these fields.

https://www.cisco.com/c/en/us/td/docs/voice_ip_comm/cucm/admin/9_1_1/ccmcfg/CUCM_BK_A34970C5_00_admin-guide-91/CUCM_BK_A34970C5_00_admin-guide-91_chapter_0111.html New QuestionWhich module is the minimum PVDM3 module needed to support video transcoding?A. PVDM3-32B. PVDM3-64C. PVDM3-128D. PVDM3-192**Answer:** C

!!!RECOMMEND!!!1.|2019 Latest 300-075 Exam Dumps (PDF & VCE) Instant Download:<https://www.braindump2go.com/300-075.html>2.|2019 Latest 300-075 Study Guide Video Instant Download: YouTube Video: <https://www.youtube.com/watch?v=S2wMYKmSgoc>