## [2018-Latest-VersionBraindump2go NS0-155 Exam PDF Dumps Instant Download[1-11

2018 January New NetApp NS0-155 Exam Dumps with PDF and VCE Free Updated Today! Following are some new NS0-155 Real Exam Questions: 1. |2018 New NetApp NS0-155 Exam Dumps (PDF & VCE) 195Q&As Download: https://www.braindump2go.com/ns0-155.html2.|2018 New NetApp NS0-155 Real Exam Question & Answers Download: https://drive.google.com/drive/folders/1MxkLZN5KA1zypVTo9BJ6WLvLiN2Rnad8?usp=sharingQUESTION 1Which two operations can be performed with the SnapDrive for windows graphical user interface?A. Create volumeB. Create Snapshot copiesC. Create FileD. Create DiskAnswer: BDExplanation:https://library.netapp.com/ecm/ecm download file/ECMM1278920 What SnapDrive doesSnapDrive software integrates with the Windows Volume Manager so that NetApp filers can serve as virtual storage devices for application data in Windows 2000 Server and Windows Server 2003 environments. SnapDrive is dependent on the virtual disk service. The virtual disk service must be started on the host prior to installing SnapDrive. SnapDrive manages virtual disks (LUNs) on a NetApp filer, making these virtual disks available as local disks on Windows hosts. This allows Windows hosts to interact with the virtual disks just as if they belonged to a directly attached redundant array of independent disks (RAID). SnapDrive provides the following additional features: It enables online storage configuration, virtual disk expansion, and streamlined management. It integrates NetApp Snapshot technology, which creates point-in-time images of data stored on virtual disks. It works in conjunction with SnapMirror?software to facilitate disaster recovery from either asynchronously or synchronously mirrored destination volumes.QUESTION 2Which storage system command would display the WWPNs of hosts that have logged into storage system using a Fibre Channel connection? A. fcp configB. fcp initiator showC. fcp show -iD. fcp show initiatorAnswer: DExplanation: <a href="https://library.netapp.com/ecmdocs/ECMP1196979/html/man1/na">https://library.netapp.com/ecmdocs/ECMP1196979/html/man1/na</a> fcp.1.htmlfcp show initiator [ -v ] [ adapter ]If no adapter name is given, information about all initiators connected to all adapters are shown. The command displays the portname of initiators that are currently logged in with the Fibre Channel target adapters. If the portname is in an initiator group setup through the igroup command, then the group name is also displayed. Similarly, all aliases set with the fcp wwpn-alias command for the portname are displayed as well. If the -v flag is given, the command displays the Fibre Channel host address and the nodename/portname of the initiators as well.QUESTION 3When using a Protection Manager policy to manage Open systems SnapValut backups on a UNIX server, which three valid objects to include in the data set? (Choose three)A. The entire clientB. A directory C. A fileD. A gtreeAnswer: ABCOUESTION 4What does it signify if the disks are "not owned" in a FAS2020 system?A. The disks are mailbox disks.B. The disks are spare disks.C. The disks are data disks.D. The disks are not used. Answer: DExplanation: Disks must be assigned to an aggregate to be used as raid group members or spares. Unassigned disks are displayed as "not owned".QUESTION 5For each Open Systems platform directory to be backed up to the SnapVault secondary storagesystem you must execute \_.A. An initial baseline copyB. A temporary copyC. An incremental copyD. A scheduled update copyAnswer: AExplanation: https://library.netapp.com/ecmdocs/ECMP1196991/html/GUID-EEBC8B52-BEA9-4B49-874F-7EC78D3F602E.htmlEach open systems platform, when prompted by the secondary system, transfers initial base images of specified directories to qtree locations on the secondary system. Note: There are no primary-side Snapshot copies in Open Systems SnapVault.QUESTION 6How does the NetApp Remote Agent (RSA) connect to NetApp Support?A. NetApp Support initiates a non-secure connection to the RSA.B. NetApp Support initiates a secure connection to the RSA.C. The RSA initiates a secure connection to NetApp Support.D. The RSA initiates a non-secure connection to NetApp support.Answer: CExplanation: https://library.netapp.com/ecm/ecm download file/ECMP1200040Remote Support Agent is the facility to provide NetApp Support Engineers with the ability to remotely trigger AutoSupport.Remote Support Agent uses HTTP or HTTPS to communicate with the storage controller to initiate commands and to collect files. It uses HTTPS to send system logs and core files from the Data ONTAP root volume to Remote Support Enterprise on the NetApp Support side. NetApp RSA is not related to the RSA public key encryption algorithm.QUESTION 7Which two commands can be used to enable LUN reservations? (Choose two)A. lun set reservationB. lun reservation setC. lun mapD. lun createAnswer: ADExplanation: https://library.netapp.com/ecmdocs/ECMP1196979/html/man1/na\_lun.1.htmllun set reservation lun\_path [ enable | disable ]Enables or disables the space reservation on the LUN. If no arguments are supplied after the lun path, then the space reservation status of the given lun\_path is displayed. lun create -s size -t ostype [ -o noreserve ] [ -e space\_alloc ] lun\_path This usage of the lun create command should be employed to create a new LUN of given size, with initially zero contents. The LUN is created at the lun\_path given. No file should already exist at the given lun path. The directory specified in the lun path must be a qtree root directory. The size is specified in bytes. Optionally, a number followed by a one-character multiplier suffix can be used: c (1), w (2), b (512), k

(1024), m (k\*k), g (k\*m), t (m\*m). The size of the created LUN could be larger than the size specified, in order to get an integral number of cylinders while reporting the geometry using SAN protocols. The size of the LUN actually created is reported if it is different from that specified in the command. The mandatory ostype argument is one of: solaris (the LUN will be used to store a Solaris raw disk in a single-slice partition), windows (the LUN will be used to store a raw disk device in a single-partition Windows disk using the MBR (Master Boot Record) partitioning style), hpux (the LUN will be used to store HP-UX data), aix (the LUN will be used to store AIX data), vld (the LUN contains a SnapManager VLD), linux (the LUN will be used to store a Linux raw disk without any partition table), netware (the LUN will be used to store NetWare data), vmware (the LUN will be used to store VMware data), windows gpt (the LUN will be used to store Windows data using the GPT (GUID Partition Type) partitioning style), windows 2008 (the LUN will be used to store Windows data for Windows 2008 systems), openvms (the LUN will be used to store Open-VMS data), xen (the LUN will be used to store Xen data), hyper v (the LUN will be used to store Hyper-V data), solaris efi By default, the LUN is space-reserved. To manage space usage manually, -o noreserve can be specified. Using this option will create a LUN without any space being reserved. Provisioning threshold events can be enabled by specifying -e space alloc option. This option has to be used in conjunction with -o noreserve.lun map [ -f ] lun\_path initiator\_group [ lun\_id ]Maps a LUN to all the initiators in the supplied group. If a LUN ID is not specified, the smallest number that can be used for the various initiators in the group is automatically picked. Note that this command can be used multiple times to configure multiple maps for a LUN, or for an initiator group. Once created, you can use lun show -m to list all the LUN mappings. The optional -f argument disables checking with the HA partner for LUN mapping conflicts.QUESTION 8Which Data ONTAP option sets system-wide for all transfers?A. Options transfers.wide.enableB. Options transfer.throttle.enable.C. Option replication.wide.enableD. Options replication.throttle.enableAnswer: DExplanation:https://library.netapp.com/ecmdocs/ECMP1196979/html/man1/na options.1.html replication.throttle.enable Enables global network throttling of SnapMirror and SnapVault transfers. The default value for this option is off.replication.throttle.incoming.max kbsThis option specifies the maximum total bandwidth used by all the incoming (applied at destination) SnapMirror and SnapVault transfers, specified in kilobytes/sec. The default value for this option is unlimited, which means there is no limit on total bandwidth used. This option is valid only when the option replication.throttle.enable is on. replication.throttle.outgoing.max\_kbsThis option specifies the maximum total bandwidth used by all the outgoing (applied at source) SnapMirror and SnapVault transfers specified in kilobytes/sec. The default value for this option is unlimited, which means there is no limit on total bandwidth used. This option is valid only when the option replication throttle enable is on OUESTION 9What is the correct format for the scheduling component of a SnapVault schedule? A. cnt[@day list][@hour list]B. YYYY-MM-DDC. Crontable formatD. List of dates in ISO Date formatAnswer: AExplanation:

https://library.netapp.com/ecmdocs/ECMP1196979/html/man1/na snapvault.1.html

http://www.geekyfacts.com/index.php?option=com\_content&view=article&id=64:snapvault snapvault snap sched [ -f ] [ -x ] [ -o options ] [volname [snapname [schedule]]] schedule is cnt[@day list][@hour list] or cnt[@hour list][@day list] In the schedule, cnt tells SnapVault how many of the snapshots to keep for primaries and for non-SnapLock secondary volumes. The snapshots will be numbered newest to oldest from 0 to cnt-1. When creating a new snapshot, SnapVault will delete the oldest snapshots, increment by one the number on the remaining snapshots and then create a new number 0 snapshot. If a snapshot is missing from the sequence (e.g. sv.0, sv.1, and sv.3 exist but sv.2 does not), only snapshots that need to be renumbered to make room for the new sv.0 snapshot will be renumbered. In the example, sv.0 and sv.1 would be renamed to sv.1 and sv.2, but sv.3 would remain unchanged. The cnt in the schedule is interpreted differently for SnapVault secondary SnapLock volumes. For SnapLock secondary volumes, snapshots are created with a name that includes an encoded date and time of when the snapshot is created. These snapshots are never renamed and they are never automatically deleted. These snapshots may be deleted using snap delete after the retention period of the snapshot has expired. If cnt is 0, no snapshots will be taken. If cnt is any non-zero value, snapshots will be taken and no snapshots will be automatically deleted. If specified, the day list specifies which days of the week the snapshot should be created. The day list is a comma-separated list of the first three letters of the day: mon, tue, wed, thu, fri, sat, sun. The names are not case sensitive. Day ranges such as mon-fri can also be given. The default day list is mon-sun, i.e. every day. If specified, the hour list specifies which hours of the day the snapshot should be created, on each scheduled day. The hour\_list is a comma-separated list of the hours during the day, where hours are integers from 0 to 23. Hour ranges such as 8-17 are allowed. Also, step values are allowed in conjuction with ranges. For example, 0-23/2 means "every two hours". The default hour list is 0, i.e. midnight on the morning of each scheduled day. OUESTION 10When will a Volume SnapMirror (VSM) from a 64-bit source to a 32-bit destination volume fail? A. When the 64-bit volumes has Volume Guarantee disabledB. When the 64-bit volume has compression enabledC. When the 64-bit volume has FlexShare enabledD. When the 64-bit volume has ASIS enabledAnswer: BExplanation: https://library.netapp.com/ecmdocs/ECMP1196986/html/GUID-87340429-8F4A-4AA6-B081-0F5040089C78.htmlData

compression requires 64-bit aggregates.QUESTION 11UNIX allows file access based on\_\_\_\_\_\_\_\_.A. NT ACLs and UNIX permissions.B. NT ACLs and SID.C. GID or UID and UNIX permissions.D. GID or UID and ACLs.Answer: CExplanation: <a href="http://hd.kvsconsulting.us/netappdoc/801docs/html/ontap/smg/GUID-866DD79D-D2A6-4FBA-">http://hd.kvsconsulting.us/netappdoc/801docs/html/ontap/smg/GUID-866DD79D-D2A6-4FBA-</a> B0BDA63560FECEFF.htmlIn OnTap 8.0, when UNIX security style is selected, only UNIX security objects can be used. The correct answer is GID, UID and UNIX permissions.Basic UNIX permissions are organized into three classes: user, group, and others. UNIX operating systems identify users with a numerical value: a user identifier, also known as a UID or User ID. Each user is a member of a group of the same name as the user. Like UIDs, groups (GIDs) are also specified using a numerical value.!!!RECOMMEND!!!1.|2018 New NetApp NS0-155 Exam Dumps (PDF & VCE) 195Q&As Download:https://www.braindump2go.com/ns0-155.html2.|2018 New NetApp NS0-155 Study Guide Video: YouTube Video: YouTube.com/watch?v=G74lQEevDwI